

PIRATE REFERENCE MANUAL

This manual is a reference for the MESA processor PIRATE. It includes descriptions of the PIRATE primitive operators. Descriptions of the PIRATE library commands and a tutorial introduction to PROCSY and PIRATE is contained in separate documents.

PIRATE REFERENCE MANUAL

This manual is a reference for the MESA processor PIRATE. It includes descriptions of the PIRATE primitive operators, descriptions of the PIRATE library commands and a tutorial introduction to PIRATE and PIRATE is contained in separate documents.

PURDUE INTERACTIVE REMOTE ACCESS TERMINAL ENVIRONMENT

R.C. SCHWABEL
MARCH 1971

FILE STRUCTURE.

PIRATE RECOGNIZES TWO GENERAL CLASSES OF DISK FILES, INTERNAL AND EXTERNAL. ALL FILES WHICH APPEAR ELSEWHERE IN THE *MACE* OPERATING SYSTEM ARE CONSIDERED EXTERNAL. THIS INCLUDES CARD IMAGE TEXT FILES, *MODIFY* OPL FILES, AND EXECUTABLE BINARY FILES OF ANY TYPE. A *PIRATE* INTERNAL FILE IS A SPECIAL FILE WHICH IS NOT CURRENTLY RECOGNIZED BY ANY OTHER PROCESSOR EXCEPT *PED*, THE PURDUE EDITOR. AN INTERNAL FILE CONTAINS ALL INDEXING INFORMATION NECESSARY TO ACCESS ANY TEXT LINE IN THE FILE WITH A MAXIMUM OF ONE *CIO* CALL. IT IS LOGICALLY COMPOSED OF A SECTION CONTAINING HEADER BLOCKS, AND A SECTION CONTAINING TEXT BLOCKS. WHILE AN INTERNAL FILE IS ACTIVE IN A *PIRATE* JOB, ALL THE HEADER BLOCKS ARE RESIDENT IN CENTRAL MEMORY AS A DOUBLY LINKED LIST. EACH HEADER BLOCK DESCRIBES ONE TEXT BLOCK, AND CONTAINS THE DISK ADDRESS OF THE TEXT BLOCK, THE CENTRAL MEMORY ADDRESS IF THE BLOCK IS IN *CM*, THE FIRST AND LAST LINE NUMBERS CONTAINED IN THE TEXT BLOCK, AND VARIOUS OTHER FLAGS USED BY THE PAGING AND TEXT MANAGEMENT ROUTINES. WHEN AN INTERNAL FILE IS CLOSED, EITHER EXPLICITLY BY A *QCLOSE* COMMAND, OR IMPLICITLY BY THE SYSTEM AT LOGOFF AND OTHER TIMES THE SYSTEM NEEDS THE SPACE OCCUPIED BY THE FILE, THE HEADER BLOCKS ARE WRITTEN TO THE DISK FILE.

THE DISK FILE IS PHYSICALLY COMPOSED OF A LEADING HEADER RECORD WHICH CONTAINS THE HEADER BLOCKS, FOLLOWED BY AS MANY 4 PRU BLOCKS AS ARE REQUIRED TO CONTAIN ALL THE TEXT BLOCKS. THE FIRST RECORD CONTAINS AS MANY HEADER BLOCKS AS WILL FIT IN 4 PRUS ON THE DISK. IF MORE HEADER BLOCKS ARE PRESENT THAN WILL FIT INTO THE FIRST RECORD, THE LAST WORD OF THE FIRST RECORD WILL BE A POINTER TO THE DISK ADDRESS OF THE REST OF THE HEADER BLOCKS.

PIRATE INTERNAL FILES MAY BE USED IN THE PURDUE EDITOR WITH A MINIMUM OF SYSTEM OVERHEAD. LIKEWISE, *PED* CAN GENERATE A *PIRATE* INTERNAL FILE IF THE *I* OPTION IS SELECTED ON THE *WRITE* COMMAND. THE *PED* *READ* COMMAND MAY BE USED TO INITIATE AN EDIT OF A *PIRATE* INTERNAL FILE, BUT A COPY OF THE FILE WILL BE MADE BEFORE THE EDITING BEGINS. THIS OPTION IS STILL FASTER THAN EDITING AN EXTERNAL FILE WITH *PED*. THE *USE* COMMAND IS THE MOST EFFICIENT MEANS OF ACCESSING A *PIRATE* INTERNAL FILE FROM *PED*. NO COPYING IS NECESSARY, JUST THE HEADER BLOCKS ARE READ INTO CENTRAL

MEMORY FROM THE FIRST RECORD OF THE FILE. THE *USE* COMMAND HAS THE DISADVANTAGE OF NOT PROVIDING A BACKUP OF THE FILE TO COVER INADVERTENT DESTRUCTION OF TEXT LINES BY AN INSUFFICIENTLY SPECIFIED CONTEXT.

THE *QDISPLAY* OPERATOR IN *PIRATE* WILL DISPLAY BOTH INTERNAL AND EXTERNAL TEXT FILES, AND MODIFY OPL FILES. INTERNAL FILES ARE ACCESSED DIRECTLY, WHERE EXTERNAL FILES MUST BE SCANNED A LINE AT A TIME IF THE DISPLAY OPERATION DOES NOT START FROM THE BEGINNING OF THE FILE.

THE *PIRATE* EDITOR REQUIRES INTERNAL MODE FILES AND WILL CONVERT AN EXTERNAL MODE FILE TO INTERNAL BEFORE ANY EDITING IS DONE. THE FILE IS LEFT IN INTERNAL MODE AFTER THE EDITING IS COMPLETE. THE USER MAY FORCE THE FILE BACK TO EXTERNAL MODE BY USING THE *QWRITE* OPERATOR. IF NO OPTIONS ARE SPECIFIED FOR THE *QWRITE* OPERATOR, AND THE FILE IS ALREADY IN EXTERNAL MODE, NO ACTION WILL BE TAKEN. HOWEVER, LINE NUMBERS MAY BE ADDED, OR THE FILE MAY BE EXPANDED OR COMPRESSED BY SPECIFYING THE PROPER OPTIONS ON THE *QWRITE* COMMAND. AN EXTERNAL FILE MAY BE FORCED INTO INTERNAL MODE FOR FASTER SCANNING BY THE *QDISPLAY* OPERATOR BY USING THE *QRI* OPERATOR. THIS OPERATOR WILL NOT TAKE ANY ACTION IF IT IS USED ON A FILE WHICH IS ALREADY IN INTERNAL MODE.

DUE TO CENTRAL MEMORY LIMITATIONS, *PIRATE* WILL ONLY KEEP A LIMITED NUMBER OF FILES IN AN ACTIVE STATUS AT ANY ONE TIME. THESE FILES ARE KEPT IN A FILE STACK WHICH IS UPDATED AT EVERY FILE REFERENCE. THE MOST RECENTLY REFERENCED FILE NAME IS ALWAYS AT THE TOP OF THE STACK. IF THE STACK BECOMES FULL, THE BOTTOM ENTRY IS DELETED AND THE FILE IS CLOSED (AS IF THE *QCLOSE* OPERATOR HAD BEEN USED) WHEN SPACE IS NEEDED FOR A NEW FILE. THE CURRENTLY ACTIVE FILE NAMES MAY BE DISPLAYED BY USING THE *FILES* OPERATOR. INFORMATION ABOUT ANY OTHER LOCAL FILES MAY BE OBTAINED BY USING THE EMESAE PROGRAM *FILETL*.

FILE NAME REQUIREMENTS

ALL LOCAL FILE NAMES MAY CONTAIN ONLY LETTERS AND NUMBERS.

ALL JOB FILE NAMES MUST ALSO START WITH A LETTER.

CERTAIN FILE NAMES ARE RESERVED AND MAY NOT BE USED. INCLUDED IN THIS GROUP ARE:

INPUT	- SYSTEM *INPUT* FILE
OUTPUT	- SYSTEM *OUTPUT* FILE
PIRMAC	- SYSTEM MACRO LIBRARY
PUNCH	- SYSTEM *PUNCH* FILE

PUNCHB - SYSTEM *PUNCHB* FILE
 PUNCHR - SYSTEM *PUNCHR* FILE
 P8 - SYSTEM *P8* FILE
 XEQTINP - XEQ SYSTEM INPUT FILE

PROCSY - PIRATE INCOMPATIBILITIES

THE FOLLOWING *PROCSY* VERSION 1.0 OPERATORS WERE IMPLEMENTED TO PROVIDE UPWARD COMPATIBILITY ONLY. THEY WERE REMOVED ON 11/05/73 AS *PIRATE* HAD BECOME FULLY OPERATIONAL. COMMAND MACROS USING THE OLD FORMS SHOULD BE CONVERTED TO THE NEW -Q- FORMS AS SOON AS POSSIBLE. THE NEW -Q- OPERATORS MAY ALSO BE USED FROM COMMAND MODE. THE ARITHMETIC OPERATORS, QADD, QSUB, QMUL, QDIVIDE, AND QCONVERT, WILL DISPLAY THE VALUE OF THE RESULT AT THE TERMINAL IF THEY ARE USED FROM COMMAND MODE.

ADD - QADD
 CONVERT - QCONVERT
 DIVIDE - QDIVIDE
 EXCHANGE - QEXCHANGE
 FILES - QFILES
 MULTIPLY - QMULTIPLY
 SET - QASSIGN
 SUBTRACT - QSUBTRACT

SINCE *PIRATE* ALLOWS 30 PARAMETERS 0≤N≤29 AND *PROCSY* ONLY ALLOWS 10, 0≤N≤9, THE MEANING OF ^PXYZ (WHERE X,Y,Z ARE NUMBERS BETWEEN 0 AND 9) IS DIFFERENT UNDER THE TWO SYSTEMS. *PIRATE* ALLOWS UP TO TWO DIGITS TO IDENTIFY A PARAMETER NUMBER. ANY *PROCSY* LINE OF THE FORM ^PXYZ SHOULD BE REWRITTEN AS ^APOXYZ TO FUNCTION THE SAME UNDER *PIRATE*.

PIRATE ALLOWS MACRO JUMPS BACKWARD AS WELL AS FORWARD. ALL MACRO JUMPS SHOULD BE CHECKED TO INSURE UNIQUE LABELS.

THE *PAR* PRIMITIVE HAS BEEN SLIGHTLY MODIFIED. THE FIRST PARAMETER IS THE NUMBER OF PARAMETERS THAT WILL BE ACCEPTED. IF NON-NULL, THE PARAMETER RANGE SPECIFIED WILL BE NULLED BEFORE USER INPUT IS ACCEPTED.

THE SECOND PARAMETER IS A PROMPT/REPROMPT CHARACTER STRING UP TO 10 CHARACTERS IN LENGTH. THIS WILL BE USED TO PROMPT THE USER FOR INPUT AND AS A REPROMPT (IN CASE A RETURN IS ENTERED).

THE THIRD PARAMETER SUPPRESSES INITIAL CARRIAGE CONTROL. IF NON-NULL, THE INITIAL CARRIAGE RETURN/LINE FEED PRECEDING THE PROMPT WILL BE SUPPRESSED. ALL REPROMPTS WILL BE PRECEDED BY A CARRIAGE RETURN/LINE FEED.

THE DEFAULTS PARAMETERS ARE ^P0-^P9. THE DEFAULT PROMPT/

REPROMPT IS A QUESTION MARK-BLANK. THE DEFAULT CARRIAGE CONTROL IS NULL.

PIRATE WILL PROCESS COMMANDS EXACTLY LIKE *PROCCY* WITH THE ADDED FEATURE, THAT ALL COMMANDS NOT IDENTIFIED AS PRIMITIVES, USER OR SYSTEM MACROS, WILL BE EXECUTED AS EMESAE PROGRAMS. AS LONG AS THERE ARE NO PRIMITIVE OR MACRO NAME CONFLICTS, THE USER MAY ENTER A EMESAE PROCESSOR BY ENTERING ITS NAME AS A COMMAND. (E.G. MUTIL, PED, ALFIE, PFILES) FOR THIS REASON, SEVERAL OF THE SYSTEM MACROFS HAVE BEEN DELETED. (E.G. ALFIE, PED)

COMMAND LINE SYNTAX.

ALL COMMAND LINES ARE PARSED BY A COMMON ROUTINE. THIS ROUTINE ISOLATES THE FIRST STRING OF ALPHANUMERIC CHARACTERS AND USES IT AS THE COMMAND NAME. EACH SUCCEEDING STRING OF ALPHANUMERIC CHARACTERS IS TAKEN AS A PARAMETER. EACH PARAMETER MAY BE UP TO 70 CHARACTERS LONG. HOWEVER, NO COMMAND MAY BE CONTINUED FROM ONE LINE TO THE NEXT. THE CHARACTERS WHICH SEPARATE EACH PARAMETER ARE SAVED AND ARE AVAILABLE TO COMMANDS AS THE -S- PARAMETERS. PARAMETERS PASSED FROM ONE MACRO TO ANOTHER MAY CONTAIN UP TO 7 CHARACTERS.

A QUOTE CHARACTER (-Q- PARAMETER) IS DEFINED WHICH ALLOWS ANY STRING OF CHARACTERS ENCLOSED BY THE QUOTE CHARACTER TO BE ENTERED AS ONE PARAMETER. THIS ALLOWS A PARAMETER TO CONTAIN CHARACTERS WHICH ORDINARILY WOULD BE CONSIDERED AS SEPARATORS.

THE CHARACTER BLANK (OR SPACE) IS CONSIDERED AS A -SOFT-SEPARATOR. A BLANK BETWEEN TWO ALPHANUMERIC PARAMETERS IS CONSIDERED AS A SEPARATOR. A BLANK FOLLOWING A SEPARATOR IS NOT CONSIDERED AS A SEPARATOR. A BLANK PRECEEDING A SEPARATOR IS NOT CONSIDERED AS A SEPARATOR EITHER.

REFORMATTING OPTIONS

THESE OPTIONS MAY BE SPECIFIED ON SEVERAL OF THE OPERATORS TO CONTROL THE REFORMATTING OF LINES IN A FILE.

FILE CONTROL.

- LL=NNN - SKIP THE FIRST *NNN-1* LINES ON THE FILE.
(LOW LINE)
- HL=NNN - STOP AFTER THE LINE *NNN*.
(HIGH LINE)
- LR=NNN - SKIP THE FIRST *NNN* RECORDS. (AN END OF FILE IS
COUNTED AS AN END OF RECORD.)
(LOW RECORD)
- HR=NNN - STOP AFTER RECORD *NNN*.
(HIGH RECORD)
- LF=NNN - SKIP THE FIRST *NNN* FILES.
(LOW FILE)
- HF=NNN - STOP AFTER THE FILE *NNN*.
(HIGH FILE)

IF -LL-, -LF-, AND -LR- ARE ALL SPECIFIED, FIRST, -LF- FILES
WILL BE SKIPPED, THEN, -LR- RECORDS WILL BE SKIPPED, AND
FINALLY, -LL- LINES WILL BE SKIPPED.

LINE CONTROL.

- TR - TRUNCATE ALL LINES TO A MAXIMUM OF 72 CHARACTERS.
- FO - DO NOT BLANK THE FIRST COLUMN OF EACH LINE AS IF IT
WERE A PRINTER FORMAT CONTROL CHARACTER.
- RS - SUPPRESS PROCESSING END OF FILES AND END OF
RECORDS.
- LC=NNN - SKIP THE FIRST *NNN-1* COLUMNS OF EACH LINE AND
TRANSFER COLUMN *NNN* AS THE FIRST COLUMN OF THE
LINE. THIS COLUMN WILL BE CONVERTED TO A BLANK
UNLESS THE -FO- OPTION IS ALSO SELECTED TO PRESERVE
THE FORMAT CONTROL CHARACTER.
(LEFT COLUMN)
- RC=NNN - DO NOT PROCESS THE COLUMNS OF EACH LINE PAST
COLUMN *NNN*. THE *TR* OPTION IS EQUIVALENT TO
RC=72.
(RIGHT COLUMN)
- LM=NNN - ADD *NNN* LEADING BLANKS TO EACH LINE.
(LEFT MARGIN)
- RM=NNN - DO NOT ALLOW THE LINE TO EXTEND PAST COLUMN *NNN*.
(RIGHT MARGIN)

IF -LC-, -RC-, -LM-, AND -RM- ARE ALL SPECIFIED, AND ARE
INCONSISTENT. I.E. $RC-LC+LM > RM$, THE RIGHT COLUMN, -RC-,
WILL BE REDUCED TO REMOVE THE INCONSISTENCY.

PARAMETER ERROR MESSAGES

THESE ERROR MESSAGES MAY BE GENERATED BY ANY OPERATOR WHICH USES A SUBSTITUTABLE PARAMETER NAME AS AN ARGUMENT.

QXX - UNRECOGNIZED PARAMETER NAME - Y
THE CHARACTER, -Y-, IS NOT THE NAME OF A SUBSTITUTABLE PARAMETER.

QXX - INVALID SUBSTITUTABLE PARAMETER NAME - Y
THE CHARACTER, -Y-, CAN NOT BE THE NAME OF A SUBSTITUTABLE PARAMETER BECAUSE IT IS NON-ALPHANUMERIC.

UNEXPECTED EOL IN PARAMETER NAME
THE PARAMETER ESCAPE CHARACTER WAS THE LAST CHARACTER IN A LINE OF TEXT TO BE SUBSTITUTED.

QXX - PARAMETER NUMBER TOO LARGE
THE NUMBER FOLLOWING A P, G, S, OR Z PARAMETER WAS GREATER THAN 29.

QXX - INVALID WIDTH PARAMETER NAME
THE NUMBER FOLLOWING A ^W WAS GREATER THAN 1.

PARAMETER SUBSTITUTION.

PARAMETER NAMES.

A	USER ACCOUNT NUMBER	(READ ONLY)
C	CURRENT TIME OF DAY CLOCK -HH:MM:SS-	(READ ONLY)
D	CURRENT DATE -MM/DD/YY-	(READ ONLY)
E	PARAMETER ESCAPE CHARACTER (^)	
F	LAST *QINSERTED* FILE NAME	(READ ONLY)
G(NN)	USER GLOBAL PARAMETERS (0≤NN≤29) (7 CHARACTERS OR LESS)	
I	USER IDENTIFIER	(READ ONLY)
J	INTEGRAL PART OF LAST LINE NUMBER *QINSERTED* IN THE FILE ^F	(READ ONLY)
L	MESA PROGRAM NEST LEVEL	(READ ONLY)
P(NN)	USER MACRO PARAMETERS (0≤NN≤29)	
Q	QUOTE CHARACTER (#)	
R	1 RANDOM DIGIT FOR EACH REFERENCE	(READ ONLY)
S(NN)	SEPARATOR CHARACTERS USED ON THE LAST MACRO CALL. (0≤NN≤29)	
T	TERMINAL IDENTIFIER (3 DIGITS)	(READ ONLY)
U	NUMBER OF ACTIVE USERS	(READ ONLY)
V	ACCOUNT NUMBER PASSWORD	(READ ONLY)
W(N)	WIDTH PARAMETER (IF N=0 OR IS OMITTED, IT IS THE WIDTH OF PARAMETERS CHECKED ON COMPARISONS IF N=1, IT IS THE WIDTH OF FILE NAMES TO	

BE SCANNED FOR COMMANDS)
 X EDIT CONTROL CHARACTER (POUND SIGN)
 Y CURRENT MACRO FILE NAME (REAL ONLY)
 Z(NN) SYSTEM SCRATCH PARAMETERS (AVAILABLE FOR USER
 USE, BUT MAY BE USED BY THE SYSTEM AT ANY
 TIME FOR ERROR MESSAGES) (0≤NN≤29)

RESERVED FOR FUTURE USE

K PARAMETER CONCATENATION CHARACTER
 O(NN) OCTAL TO CHARACTER CONVERSION

BROADCAST - SEND A MESSAGE TO THE MONITOR TERMINAL.

QBROADCAST - SEND A MESSAGE TO MONITOR TERMINAL

BRO[BROADCAST]

THE USER WILL BE ISSUED A PROMPT TO ENTER HIS MESSAGE.

CHECK - TEST FOR LOCAL FILE EXISTENCE

CHE[CK],FILE-NAME,LABEL

IF *FILE-NAME* IS A LOCAL FILE, SKIP TO *LABEL*,
 OTHERWISE CONTINUE.

CTL - SET CONTROL - B RESPONSE

CTL,X,Y,Z

WHERE: X IS THE COMMAND LINE TO BE EXECUTED AFTER
 A CONTROL-B.
 Y IF PRESENT, WILL FORCE EXECUTION OF THE
 NEXT COMMAND IN THE CURRENT MACRO.
 Z IF PRESENT, WILL FORCE A SKIP TO THE LINE
 LINE *X* IN THE CURRENT MACRO, WHERE
 X IS A LABEL OR INTEGER LINE NUMBER.

GOTO - MACRO LINE TRANSFER PROCESSOR

 GOT[0],LINE

WHERE: LINE WILL BE TAKEN AS A LINE NUMBER IF IT IS NUMERIC. IT WILL BE TAKEN AS THE FIRST CHARACTERS OF A LINE IF ALPHANUMERIC.

 IFFEQUAL - MACRO PARAMETER EQUALITY TEST

IFE[0],A,B,LABEL

IF *A* IS EQUAL TO *B*, TRANSFER TO LINE, *LABEL*.
 IF *LABEL* IS NON-NUMERIC, IT SPECIFIES THE FIRST CHARACTERS OF A LINE IN THE MACRO. IF NUMERIC, IT SPECIFIES THE LINE NUMBER TO BE PROCESSED NEXT.

IFGT - MACRO GREATER THAN TEST

IFG[T],A,B,LABEL

IF *A* IS GREATER THAN *B*, TRANSFER TO LINE, *LABEL*.
 IF *LABEL* IS NON-NUMERIC, IT SPECIFIES THE FIRST CHARACTER OF A LINE. OTHERWISE IT SPECIFIES A LINE NUMBER.

IFLT - MACRO PARAMETER LESS THAN TEST

IFL[T],A,B,LABEL

IF *A* IS LESS THAN *B*, TRANSFER TO THE LINE *LABEL*.
 IF *LABEL* IS NON-NUMERIC, IT SPECIFIES THE FIRST CHARACTERS OF A LINE IN THE MACRO. IF NUMERIC, IT SPECIFIES A LINE NUMBER IN THE MACRO.

IFNOTEQUAL - MACRO PARAMETER VALUE NOT EQUAL TEST

IFN[E],A,B,LABEL

IF *A* IS NOT EQUAL TO *B*, TRANSFER TO LINE, *LABEL*.

IF *LABEL* IS NON-NUMERIC, IT SPECIFIES THE FIRST CHARACTERS OF A LINE. OTHERWISE IT SPECIFIES A LINE NUMBER.

JOBCARD - INITIALIZE *JOBCA* FILE

JOB[CA][,A=ACCT,NAME][,JOB CARD PARAMETERS]

INITIALIZE THE FILE *JOBCA* WITH A JOB CARD. IF THE *A=ACCT,NAME* OPTION IS SPECIFIED, THE JOB CARD WILL USE -ACCT-, AND -NAME-. IF IT IS NOT SPECIFIED, THE CURRENT VALUES OF THE PARAMETERS -A- AND -N- WILL BE USED. THE JOB CARD PARAMETERS PASSED AS OPTIONS ON THE -JOB CARD- OPERATOR MAY BE ANY OPTIONS FOR A STANDARD EMACEE JOB CARD. NO VALIDATION IS DONE BY THE -JOB CA- OPERATOR.

IF THE FIRST CHARACTERS SPECIFIED AFTER THE COMMAND NAME ARE *G=TEXT* THE TERMINAL NUMBER AND NAME AND ACCOUNT NUMBER WILL BE OMITTED. THE STRING *TEXT* WILL BE THE ONLY CONTENTS OF THE FIRST LINE OF THE JOB CARD FILE.

LABEL - DEFINE A MACRO TRANSFER LABEL

LARXXX

DEFINES THE LABEL *LABXXX*

LOG - LOGOFF PROCESSOR

PARAMETERS - REQUEST USER PARAMETER ENTRY

PAR[AMETERS,PARNAME,[Q PROMPT/REPROMPT Q]],[SUPPRESS]

REQUEST A LINE OF INPUT FROM THE TERMINAL AND BREAK IT DOWN INTO PARAMETERS. *PARNAME* IS THE NUMBER OF PARAMETERS THAT WILL BE ACCEPTED FROM THE LINE. ALL PARAMETERS DESIGNATED WILL BE MADE NULL BEFORE ENTRY. IF MORE PARAMETERS ARE ENTERED, THEY WILL BE IGNORED.

PARNAME MAY BE EITHER: (DEFAULT IS P10)

1. *NN*: A NUMBER BETWEEN 1 AND 30, TO STORE THE RESULTS IN THE FIRST *NN* USER (P) PARAMETERS.
2. *PNN*: WHERE *NN* IS A NUMBER BETWEEN 1 AND 30, TO STORE THE RESULTS IN THE FIRST *NN* *P* PARAMETERS ALSO.
3. *GNN*: WHERE *NN* IS A NUMBER BETWEEN 1 AND 30, TO STORE THE RESULTS IN THE FIRST *NN* GLOBAL (G) PARAMETERS.

IF A *PROMPT/REPROMPT* CHARACTER STRING IS ENTERED, THE FIRST TEN CHARACTERS WILL BE USED TO PROMPT/REPROMPT THE USER. IF THE *SUPPRESS* PARAMETER IS NON-NULL, THE CARRIAGE RETURN/LINE FEED WHICH NORMALLY PRECEEDS THE INITIAL PROMPT WILL BE SUPPRESSED. REPROMPTS WILL ALWAYS BE PRECEDED BY A CARRIAGE RETURN/LINE FEED.

ERROR MESSAGES:

PAR - ILLEGAL ARGUMENT - XX
 THE PARAMETER, -XX- MAY NOT BE CHANGED.

QACCESS - ACCESS A JOB FROM THE BATCH SYSTEM

QAC[CESS],JOBNAME[,OPTIONS]

WHERE:

JOBNAME = THE NAME OF THE DESIRED JOB OUTPUT. THIS NAME MUST MATCH THE NAME USED TO #OPEN# THE JOB TO THE BATCH SYSTEM AND IS THE NAME RETURNED AS THE RESULT OF A #STATUS# COMMAND.

OPTIONS = AN ARBITRARY NUMBER OF FORMAT CONTROL OPTIONS. FROM 0 TO 29 OPTIONS MAY BE SPECIFIED AND MAY BE IN ANY ORDER. OPTIONS SHOULD BE SEPARATED BY SEPARATOR CHARACTERS.

AVAILABLE OPTIONS: (IF STATED, MEANS...)

SA - SAVE THE BATCH JOB OUTPUT FILE. NORMALLY THIS FILE IS RELEASED AFTER BEING ACCESSED.

NO - SUPPRESS THE INITIAL DAYFILE PRINTOUT.

NW - DO NOT WAIT IF THE FILE IS NOT IN THE PRINT QUEUE.

PR - ACCESS PRINT (OUTPUT) QUEUE FILE.

- PH - ACCESS PUNCH (HOLLERITH) QUEUE FILE.
- PB - ACCESS PUNCH (BINARY) QUEUE FILE.
- PA - ACCESS PUNCH (80 COLUMN) QUEUE FILE.
- TR - TRUNCATE ALL LINES RETRIEVED TO A MAXIMUM OF 72 CHARACTERS.
- FO - PRESERVE THE PRINTER FORMAT CONTROL CHARACTER ON EACH LINE OF OUTPUT DATA.
- RS - SUPPRESS PRINTING OF \uparrow EOR AND \uparrow EOF MESSAGES AT END OF RECORD AND END OF FILE POINTS IN THE OUTPUT FILE. THE END OF RECORD AND END OF FILE MARKS ARE LIKEWISE NOT TRANSFERRED TO THE LOCAL FILE.
- LLNNN - START LINE RETRIEVAL AT LINE NNN.
- HLNNN - STOP LINE RETRIEVAL AT LINE NNN.
- LRNNN - START LINE RETRIEVAL AT RECORD NNN. THE FIRST RECORD IS NUMBERED 00. BOTH END OF RECORD AND END OF FILES ARE COUNTED DURING THE SKIPPING PROCESS.
- HRNNN - STOP LINE RETRIEVAL AT RECORD NNN.
- LFNNN - START LINE RETRIEVAL AT FILE NNN. THE FIRST FILE IS NUMBERED 00. ONLY END OF FILES ARE COUNTED DURING THE SKIPPING PROCESS.
- HFNNN - STOP LINE RETRIEVAL AT FILE NNN.
- LCNNN - NNN IS THE LEFTMOST COLUMN OF EACH LINE IMAGE IN THE BATCH JOB OUTPUT FILE TO BE SENT TO THE TERMINAL DATA FILE. COLUMN NNN WILL BE RELOCATED TO THE COLUMN 0 POSITION AND WILL BE SUBJECT TO FORMAT CHARACTER SUPPRESSION UNLESS SUPPRESSION IS NEGATED BY THE \neq FO \neq OPTION.
- RCNNN - NNN IS THE RIGHTMOST COLUMN TO BE SENT.
- LMNNN - NNN IS THE LEFT MARGIN POSITION FOR THE OUTPUT LINE IMAGE AT THE TERMINAL.
- RMNNN - NNN IS THE RIGHT MARGIN. CHARACTERS IN THE ORIGINAL LINE IMAGE THAT WOULD HAVE PRINTED TO THE RIGHT OF NNN WILL NOT BE RETRIEVED FROM THE BATCH OUTPUT FILE.

ANY PARAMETER OF THE FORM *XXNNN* MAY BE ENTERED AS:
XX=NNN.

DEFAULTS:

SA - RELEASE THE OUTPUT FILE AFTER RETRIEVAL.
 NO - RETURN DAYFILE DATA BEFORE AND AFTER THE OUTPUT
 DATA FROM THE BATCH JOB.
 NW - WAIT FOR THE JOB TO COMPLETE, IF NOT ALREADY IN
 OUTPUT QUEUE.
 PR - ACCESS PRINT (OUTPUT) QUEUE FILE.
 TR - NOT SET - RETURN THE FULL LINE IMAGE.
 FO - REPLACE FORMAT CHARACTERS WITH A BLANK.
 RS - PRINT ^EOR AND ^EOF MESSAGES.
 LLNNN - NNN = 000
 HLNNN - NNN = 262,143
 LRNNN - NNN = 000
 HRNNN - NNN = 262,143
 LFNNN - NNN = 000
 HFNNN - NNN = 262,143
 LCNNN - NNN = 000
 RCNNN - NNN = 140
 LMNNN - NNN = 000
 RMNNN - NNN = 070

ERROR MESSAGES:

QAC - ILLEGAL COMMAND FROM BATCH
 BATCH MODE *PIRATE* IS NOT ALLOWED TO
 SEND OR ACCESS JOBS FROM THE BATCH SYSTEM.

QAC - INVALID JOB NAME - (NAME)
 THE SUPPLIED JOBNAME CONTAINED SPECIAL
 CHARACTERS WHICH ARE NOT LEGAL IN A JOB
 NAME IN THE MACE OPERATING SYSTEM.

QAC - NULL JOB NAME
 NO JOBNAME WAS SPECIFIED.

QAC - (IIINAME) IS A LOCAL FILE
 THE FILE NAME FORMED BY CONCATENATING THE
 3 CHARACTER USER ID WITH THE SUPPLIED
 JOB NAME ALREADY EXISTED AS A LOCAL FILE.

QAC - INVALID OPTION - XX
 THE OPTION, -XX-, IS NOT A VALID OPTION
 FOR THE *QACCESS* OPERATOR.

NOTES:

- AFTER *QACCESS* HAS BEEN TYPED THE TERMINAL WILL BE INTERLOCKED UNTIL THE DATA RETRIEVAL OPERATION HAS BEEN COMPLETED.
FOR LARGE FILES THIS MAY BE SEVERAL MINUTES.
- CTRL-B MAY BE STRUCK AT ANY TIME DURING *QACCESS*. IF THE RESPONSE IS NOT IMMEDIATE THE FILE IS IN THE PROCESS OF BEING COPIED TO A LOCAL DATA FILE AND CANNOT BE INTERRUPTED.
- AFTER STRIKING CTRL-B, A *FILES* OPERATOR SHOULD BE USED TO CHECK FOR COMPLETION OF THE ABORTED ACCESS AND CONSEQUENT ENTRY OF THE DATA FILE NAME INTO THE USERS FILE CATALOG.
- AVAILABILITY OF OUTPUT FILES MAY BE DETERMINED BY TYPING *STATJS*. ONLY FILES IN THE OUTPUT QUEUE MAY BE RETRIEVED WITHOUT SUBSTANTIAL INTERLOCK DELAY TIMES.
- THE *NW* OPTION MAY BE USED IN A MACRO TO PROVIDE CONDITIONAL ACCESS OF A JOB. THE *CHECK* OPERATOR CAN BE USED AFTER THE *QACCESS* OPERATOR TO DETERMINE IF THE JOB WAS ACCESSED OR NOT. THE MACRO CAN THEN ASK WHETHER THE USER WISHES TO TRY AGAIN OR ATTEMPT THE ACCESS LATER.

QADD - ADD PARAMETER VALUES

QAD[D],PARM1[,PARM2][,8][,R]
 WHERE PARM2 WILL DEFAULT TO THE VALUE *1* IF OMITTED,
 IF *8* IS THE THIRD PARAMETER, OCTAL BASE ARITHMETIC
 WILL BE USED,
 AND, IF *R* IS THE FOURTH PARAMETER, THE RESULT WILL
 BE LEFT RIGHT JUSTIFIED IN THE PARAMETER.

ERROR MESSAGES:

QAD - ILLEGAL RESULT PARAMETER - X
 THE PARAMETER X MAY NOT BE CHANGED.

QAPPEND - APPEND ONE FILE TO ANOTHER

QAP[PEND],FROM,TO[,OPTIONS]

WHERE:

- FROM- IS THE FILE TO BE COPIED FROM.
- TO- IS THE FILE TO BE COPIED TO. IF -TO- EXISTS, IT WILL BE POSITIONED BEFORE ITS END-OF-INFORMATION BEFORE THE -FROM- FILE IS APPENDED TO IT.
- OPTIONS- MAY BE ANY -QACCESS- OPTION, AND
- IN=NNN- SET THE INCREMENT BETWEEN LINES TO -NNN-. IF NOT SPECIFIED, THE INCREMENT WILL BE TAKEN FROM THE DIFFERENCE BETWEEN EACH SUCCESSIVE PAIR OF LINES IN THE FILE -FROM-.

ALL FILE POSITIONING AND REFORMATTING OPTIONS ARE VALID, AND APPLY TO THE FILE -FROM-.

ERROR MESSAGES:

QAP - NO DESTINATION FILE

THE DESTINATION FILE NAME WAS MISSING OR NULL.

QAP - NULL SOURCE FILE NAME

THE SOURCE FILE NAME WAS NULL.

QAP - INVALID OPTION -XX

THE OPTION, -XX-, IS NOT A VALID FILE REFORMATTING OPTION RECOGNIZED BY *QAPPEND*

QASSIGN - ASSIGN VALUE TO PARAMETERS

QAS[IGN], PARM-NAME, VALUE

ASSIGN THE STRING *VALUE* TO THE PARAMETER *PARM-NAME*.

PARAMETER NAMES WHICH CAN BE SET USING THE *QASSIGN* OPERATOR:

- P0 - P29 - MACRO ARGUMENT PARAMETERS.
- G0 - G29 - GLOBAL PARAMETERS.
- E - PARAMETER ESCAPE CHARACTER (^)
- Q - QUOTE CHARACTER (")
- W[0] - WIDTH OF PARAMETER NAMES CHECKED BY THE COMPARISON OPERATORS (36). IF THE VALUE IS SET TO ZERO OR GREATER THAN 42, THE ENTIRE PARAMETER VALUE WILL BE SCANNED.
- W1 - BIT WIDTH OF FILE NAMES USED AS COMMANDS (30). IF SET TO ZERO OR GREATER THAN 42, THE ENTIRE NAME WILL BE USED.
- X - EDIT CONTROL CHARACTER (␣).

- QCO - ILLEGAL RESULT PARAMETER - XX
THE PARAMETER -XX- MAY NOT BE CHANGED.
- QCO - NULL RESULT PARAMETER NAME
THE RESULT PARAMETER NAME MAY NOT BE NULL.
- QCO - INVALID NUMBER (NNNNN)
THE NUMBER SUPPLIED COULD NOT BE CONVERTED
TO BINARY UNDER THE CONVERSION MODE
SPECIFIED.

QCREATE - CREATE A NEW LOCAL FILE

QCREATE],LFN[,OPTIONS]

WHERE *OPTIONS* MAY BE ANY OF THE FOLLOWING:

- *TR* = TRUNCATE THE LINES TO A MAXIMUM OF
72 CHARACTERS.
- *LCNN* = DO NOT USE THE FIRST *NN*
CHARACTERS OF EACH LINE ENTERED.
- *RCNN* = TRUNCATE EACH LINE AT COLUMN
NN.
- *LMNN* = INSERT *NN* LEADING BLANKS AT
THE BEGINNING OF EACH LINE ENTERED.

ERRORS:

- QCR - INVALID OPTION - XX
INVALID OPTION SPECIFIED IN QCREATE CALL

QDELETE - DELETE LOCAL FILES

QDE[LETE],FILE1[,FILE2][, ...][,FILEN]

DELETES ALL DISK SPACE OCCUPIED BY A LOCAL FILE. PERMANENT
AND COMMON FILES ARE RETURNED TO THE SYSTEM AND ARE NO LONGER
ACCESSABLE.

1. FILE NAMES > 9999999 WILL NOT BE DELETED.
2. IF THE CURRENT MACRO INPUT FILE IS TO BE DELETED,
CONTROL WILL RETURN TO THE COMMAND MODE.
3. IF ANY OF THE FILES HAS BEEN DECLARED AS A MACRO
LIBRARY FILE, THE MACRO LIBRARY DIRECTORY ENTRIES
FOR ALL RECORDS IN THE FILE WILL BE DELETED.
4. RESERVED FILE NAMES WILL NOT BE DELETED.

QDISPLAY - DISPLAY A LOCAL FILE

QDI[SPLAY],FILE[,LINE1][,LINE2][,OPTIONS]

WHERE:

LINE1 AND *LINE2*, IF SPECIFIED, MAY BE EITHER INTEGER OR DECIMAL NUMERIC LINE NUMBERS, OR A QUOTED CHARACTER STRING IDENTIFYING A LINE. IF EITHER CHARACTER STRING IS ALL ALPHANUMERIC AND STARTS IN COLUMN 1 OF THE LINE, IT NEED NOT BE ENCLOSED IN QUOTES. IF THE COLUMN THAT THE CHARACTER STRING STARTS IN IS KNOWN, IT MAY BE SPECIFIED IMMEDIATELY FOLLOWING THE TERMINATING QUOTE OF THE STRING. IF NO COLUMN NUMBER IS SPECIFIED FOR A QUOTED STRING, THE ENTIRE LINE WILL BE SEARCHED FOR THE CHARACTER STRING.

OPTIONS MAY BE ANY OF THE FILE REFORMATTING OPTIONS EXCEPT, -LL-, AND -HL-. IN ADDITION, THE FOLLOWING OPTIONS ARE RECOGNIZED BY -QDISPLAY-.

SUP - TO SUPPRESS LINE NUMBER PRINTOUT, AND

PAR,N - TO CRACK THE LINE INTO PARAMETERS AS IF IT HAD BEEN ENTERED WITH THE *PAR* OPERATOR.

ERROR MESSAGES:

QDI - INVALID OPTION - XX

THE OPTION, -XX-, HAS NO MEANING FOR THE *QDISPLAY* OPERATOR.

QDIVIDE - DIVIDE PARAMETER VALUES

QDV[IDE],PARM1[,PARM2][,8][,R]

ARGUMENTS ARE IDENTICAL TO *ADD*.

QEDIT - EDIT A LOCAL FILE

QED[IT],FILE

COMMAND SYNTAX:

OPTIONAL PARTS OF THE EDITOR DIRECTIVES ARE ENCLOSED IN SQUARE BRACKETS -[]-.

ONLY THE FIRST CHARACTER OF ALL EDIT COMMANDS EXCEPT -EOR-, -EOF-, AND -EOI- IS SIGNIFICANT. ANY ALPHANUMERIC CHARACTERS

FOLLOWING THE FIRST WILL BE IGNORED.

LN=(LINE TEXT)(CR) ENTER OR REPLACE LINE NUMBER *LN*
 LN,INCR=(LINE TEXT)(CR) ENTER OR REPLACE LINE NUMBER
 LN AND PROMPT WITH INCREMENTS OF *INCR*.

D,LN(CR) DELETES LINE NUMBER *LN*
 D,LN1,LN2(CR) DELETES LINE NUMBER *LN1* THROUGH *LN2*
 LN1[,LN2]D(CR) (DITTO)

R,LN(CR) REPLACES LINE NUMBER *LN*
 [LN]R(CR) (DITTO)

A(CR) ADDS LINES OF TEXT AT THE END OF THE FILE
 A,LN(CR) ADDS LINES OF TEXT AFTER *LN*
 A,LN,INCR(CR) ADDS LINES OF TEXT STARTING AT *LN* WITH
 AN INCREMENT OF *INCR*
 [LN[,INCR]]A(CR) (DITTO)

I,LN(CR) INSERTS LINES OF TEXT STARTING AT *LN* WITH
 INCREMENT OF 0.01
 I,LN,INCR(CR) INSERTS LINES OF TEXT STARTING AT *LN*
 WITH INCREMENT *INCR*.
 [LN[,INCR]]I(CR) (DITTO)

EOR(CR) WRITES AN END OF RECORD ON THE FILE
 EOF(CR) WRITES AN END OF FILE ON THE FILE
 FOI(CR) TERMINATES THE EDITING SESSION

S(CR) TERMINATES THE EDITING SESSION.

[PRINT](CR) PRINTS THE CURRENT LINE.
 P[PRINT],LN(CR) PRINTS LINE -LN-.
 P[PRINT],LN,LN2(CR) PRINTS LINE -LN- THROUGH LINE -LN2-.
 [LN[,LN2]][PRINT](CR) (DITTO)

NOTE: THE CHARACTER Q IN THE FOLLOWING COMMANDS REPRESENTS
 THE CURRENT QUOTE CHARACTER. IF THE DESIRED STRING
 DOES NOT CONTAIN ANY SEPARATOR CHARACTERS AND STARTS
 IN COLUMN 1, THE QUOTES MAY BE OMITTED.

[LN]C[CHANGE],Q STRING1 Q[COL]=Q STRING2 Q(CR)
 CHANGES THE OCCURANCE OF -STRING1- IN COLUMN -COL- TO
 -STRING2-. IF NO COLUMN NUMBER, -COL-, IS SPECIFIED,
 THE FIRST OCCURANCE OF -STRING1- IN THE LINE WILL BE
 CHANGED.

[LN[,LN2]]F[IND],Q STRING Q[COL](CR)
 FINDS THE FIRST OCCURANCE OF STRING -STRING- STARTING
 IN COLUMN -COL- IN THE FILE BETWEEN LINE -LN- AND
 LINE -LN2-. IF -LN2- IS NOT SPECIFIED, THE END OF THE
 FILE WILL BE ASSUMED. IF -LN- IS NOT SPECIFIED, THE
 LINE AFTER THE MOST RECENTLY USED LINE WILL BE USED.
 IF -COL- IS NOT SPECIFIED, ALL COLUMNS OF THE LINES

WILL BE SEARCHED FOR THE STRING.

THE QUOTE CHARACTER MAY BE CHANGED DURING THE EXECUTION OF THE EDITOR WITH THE FOLLOWING COMMAND.

Q[QUOTE]=C(CR)

THE CHARACTER -C- WILL BE TAKEN AS THE QUOTE CHARACTER FOR THE REMAINDER OF THE EDITOR SESSION. THE ORIGINAL QUOTE CHARACTER WILL BE RESTORED UPON EXITING THE EDITOR.

NOTE:

ANY LINE WHICH BEGINS WITH A LINE NUMBER PROMPT MUST HAVE THE EDIT CONTROL CHARACTER AS THE FIRST COLUMN, FOLLOWED BY THE EDIT COMMAND.

ERROR MESSAGES:

ILLEGAL CURRENT COMMAND FILE EDIT

THE CURRENT COMMAND MACRO FILE MAY NOT BE EDITED WHILE IT IS BEING USED FOR MACRO COMMAND INPUT.

QED - (NAME) DOES NOT EXIST

THE FILE TO BE EDITED MUST BE EITHER A LOCAL FILE OR A LIBRARY MACRO RECORD NAME.

ILLEGAL SYNTAX

THE LAST COMMAND WAS NOT RECOGNIZED BY THE EDITOR.

NO SUCH LINE

THE EDITOR FAILED TO FIND THE REQUESTED LINE.

NO SUCH SUBSTRING

THE CHANGE FUNCTION COULD NOT LOCATE STRING1.

QEN - SET ENVIRONMENT VARIABLES FOR TERMINAL

QEN [P1][,P2]...[,PN]

WHERE: PN ARE EQUIVALENCED PARAMETERS OF ONE OF THE FOLLOWING FORMS:

1. PARAM = VALUE ASSIGN THE VALUE TO THE NAMED PARAMETER
2. PARAM RESET THE PARAM TO THE DEFAULT VALUE

THE LEGAL PARAMS AND VALUES ARE:

(FOR THE FOLLOWING, NN REPRESENTS A DECIMAL NUMBER)

WIDTH=NN PAGE WIDTH IN COLUMNS (0≤WIDTH≤144)
 DEPTH=NN PAGE DEPTH FOR CRT DEVICES
 EJECT=NN EJECT COUNT FOR TTY DEVICES
 (NUMBER OF LINES TO SPACE AFTER -DEPTH- LINES.)
 DUPLEX=FULL/HALF SET TRANSMISSION MODE TO FULL (HALF) DUPLEX

(FOR THE FOLLOWING, NN REPRESENTS AN OCTAL NUMBER)

EOL=NN / ON / OFF SET END OF LINE CHARACTER
 RUBOUT=NN / ON / OFF SET RUBOUT CHARACTER
 BKSP=NN / ON / OFF SET BACKSPACE CHARACTER

CRLF=ON / OFF DISABLE AUTO CR/LF INSERTION
 PR1=ON / OFF PROCSY1 COMPATIBILITY MODE
 SUSPEND=ON / OFF ENABLE (DISABLE) SUSPEND
 TAPE=ON / OFF ENABLE (DISABLE) PAPER TAPE MODE

EXAMPLE:

QEN BKSP=10,EOL=OFF

NOTES:

1. IF THE SAME PARAMETER NAME IS USED MORE THAN ONCE IN THE SAME COMMAND LINE -- ONLY THE LAST OCCURRENCE OF THE PARAMETER WILL BE CHANGED. FOR EXAMPLE,
 QEN BKSP=10,BKSP=OFF
 WILL MERELY DISABLE THE USE OF BACKSPACE. IT WILL NOT CHANGE THE VALUE OF THE BACKSPACE CHARACTER TO 10.
2. THE WORDS *ON* AND *ENABLE* ARE SYNONYMOUS AS ARE *OFF* AND *DISABLE*.
3. NOTE THAT OCTAL VALUES, WHERE USED, ARE NOT SUFFIXED BY A *B*.

QERROR - SET OPERATOR ERROR RESPONSE

QER[ROP],X,Y,Z

WHERE:

- X = THE COMMAND TO BE EXECUTED AFTER A COMMAND ERROR.
 Y = IF PRESENT, WILL FORCE THE EXECUTION OF THE NEXT LINE IN THE CURRENT MACRO AFTER THE FIRST COMMAND ERROR.
 Z = IF PRESENT, WILL FORCE A SKIP TO THE LINE *X* IN THE CURRENT MACRO, WHERE *X* IS A LABEL OR INTEGER LINE NUMBER.

QEXCHANGE - EXCHANGE PARAMETER ENTRIES

QEX[CHANGE],PARM1[,PARM2]

EXCHANGE THE VALUES OF *PARM1* AND *PARM2*.

IF *PARM2* IS NOT SPECIFIED, *PARM1* WILL BE CLEARED.
SEE THE *QASSIGN* OPERATOR FOR A LIST OF PARAMETERS WHICH MAY
BE USED AS -PARM1- AND -PARM2-.

ERROR MESSAGES:

QEX - INSUFFICIENT NUMBER OF ARGUMENTS
AT LEAST ONE ARGUMENT MUST BE SUPPLIED.

QEX - ILLEGAL ARGUMENT -XX
THE PARAMETER, -XX-, MAY NOT BE CHANGED.

QFILES - DISPLAY ACTIVE LOCAL FILE NAMES

QFI[LES][,FILE-NAME]

THE NAMES OF THE ACTIVE FILES WILL BE WRITTEN ON THE FILE,
FILE-NAME, IF PRESENT. OTHERWISE, THEY WILL BE WRITTEN
TO THE TERMINAL.

THE FORM OF THE OUTPUT IS:

FNAME MODE LINE NUMBER

WHERE:

FNAME IS THE NAME OF THE FILE.

MODE IS *I* FOR AN INTERNAL (EDITOR) FILE
OR *E* FOR AN EXTERNAL (DISK IMAGE)
MODE FILE.

LINE NUMBER IS THE LINE NUMBER OF THE
CURRENT FILE POSITION.

ACTIVE FILE STACK WILL BE LISTED BY THE *QFI* OPERATOR.
THESE FILES WILL BE LISTED IN THE ORDER OF MOST RECENT USE.
FOR A COMPLETE LIST OF LOCAL FILES USE THE PROGRAM EFFLETBLE.

QFLUSH - FLUSH OUTPUT TERMINAL BUFFER

QFL[USH][,WAIT]

FLUSH THE OUTPUT BUFFER TO THE TERMINAL.

IF THE WAIT PARAMETER IS NON-NULL, WAIT UNTIL TERMINAL OUTPUT IS COMPLETE BEFORE CONTINUING.

QHOLD - INACTIVATE TERMINAL

QHO[LD]

QINSERT - INSERT LINES IN A FILE

QIN[INSERT] Q TEXT STRING Q[,FILE][,LINE]

WHERE: *Q* IS THE CURRENT QUOTE CHARACTER.
 TEXT STRING IS THE TEXT LINE TO BE INSERTED
 (MUST NOT CONTAIN THE CURRENT QUOTE CHARACTER)
 FILE IS THE FILE THAT THE LINE SHOULD BE INSERTED INTO. DEFAULTS TO *JOBCA*.
 LINE IS THE LINE NUMBER TO BE USED. DEFAULTS TO THE NEXT INTEGRAL LINE NUMBER AFTER THE END OF THE FILE.

QIQUIRE - INQUIRE ABOUT BATCH SYSTEM JOBS

QIQ[UIRE][,FILENAME][,JOBNAME1][...][,JOBNAME]

WRITE THE STATUS OF THE REQUESTED JOBS ON *FILENAME*.
 1. IF NO JOBNAMES ARE SUPPLIED, ALL JOBS FROM THIS TERMINAL WILL BE FOUND.
 2. IF NO FILENAME IS SUPPLIED, THE JOB STATUS WILL BE WRITTEN DIRECTLY TO THE TERMINAL.

QLIBRARY - DECLARE A MACRO LIBRARY FILE

QLI[BRARY],FILE1[,FILE2][.....][,FILE]

DECLARES FILE1,FILE2,.....FILEN AS MACRO LIBRARY FILES WITH A LIBEDIT DIRECTORY AT THE END.
 ALL RECORDS OF TYPE *TEXT* OR *OPL* ON THE LIBRARY FILES MAY

BE USED AS MACRO NAMES.

THE FILES ARE PROCESSED IN A LEFT TO RIGHT ORDER. IF AN ERROR IS DETECTED WHILE PROCESSING ANY OF THE FILES, THE REMAINING FILES WILL NOT BE PROCESSED.

ERROR MESSAGES:

QLI - (NAME) DOES NOT EXIST
THE FILE *NAME* IS NOT A LOCAL FILE.

QLI - NO LIBRARY DIRECTORY FOUND - (NAME)
THE FILE *NAME* DID NOT HAVE A *LPREDIT*
DIRECTORY AS ITS LAST RECORD.

QLL - LIBRARY LIST

QLL,[FILENAME][,LIBRARY1]...[,LIBRARYN]

LISTS THE DIRECTORIES FOR THE SPECIFIED LOCAL LIBRARIES ONTO FILE *FILENAME*. IF *FILENAME* IS NULL, THE DIRECTORIES WILL BE LISTED AT THE TERMINAL. IF NO LIBRARY NAMES ARE SPECIFIED, THEN ALL DIRECTORIES WILL BE LISTED.

QMULTIPLY - MULTIPLY PARAMETER VALUES.

QMULTIPLY],PARM1[,PARM2][,8][,R]
ARGUMENTS ARE IDENTICAL TO *ADD*.

QPAUSE - INACTIVATE TERMINAL FOR A PREDETERMINED TIME

QPA[USE],TIME

- HAS NO EFFECT IN BATCH MODE
- TIME DEFAULTS TO 300 SECONDS IF LARGER VALUE GIVEN

QRENAME - RENAME A LOCAL FILE

QRE[NAME],OLDNAME,NEWNAME

1. IF THE OLD FILE HAS BEEN DECLARED AS A MACRO LIBRARY FILE, THE MACRO LIBRARY DIRECTORY ENTRIES FOR ALL RECORDS ON THE FILE WILL BE DELETED.
2. FILE NAMES > 9999999 WILL NOT BE RENAMED.
3. LOCKED (READ ONLY) FILES WILL NOT BE RENAMED.
4. IF THE FILE TO BE RENAMED IS THE CURRENT MACRO INPUT FILE, THE MACRO INPUT WILL CONTINUE FROM THE FILE WITH THE NEW NAME.
5. FILES WILL NOT BE GIVEN NAMES > 9999999.
6. RESERVED FILES WILL NOT BE RENAMED.

ERROR MESSAGES:

QRE - FILE [(NAME)] DOES NOT EXIST
THE OLD FILE COULD NOT BE LOCATED.

QRE - (NAME) ALREADY EXISTS
THE NEW FILE NAME ALREADY EXISTS AS A LOCAL FILE.

QRE - NULL OLD FILE NAME
THE OLD FILE NAME MUST BE NON-NULL.

QRE - LOCKED FILE [(NAME)] NOT RENAMED
THE FILE *NAME* WAS NOT RENAMED BECAUSE IT WAS WRITE PROTECTED (LOCKED).

QRE - NULL NEW FILE NAME
NO NEW FILE NAME WAS SPECIFIED.

QRI - READ FILE INTO INTERNAL FORMAT

QRI, FILE[, OPTIONS]

CONVERTS A FILE FROM EXTERNAL MODE TO INTERNAL MODE FOR EDITING AND FASTER SCANNING FOR LINE NUMBERS.

WHERE: -OPTIONS- MAY BE ANY OF THE FILE OR LINE REFORMATTING OPTIONS.

IF THE FILE IS THE CURRENT MACRO INPUT FILE, CONTROL WILL RETURN TO COMMAND MODE AFTER THIS OPERATOR.

ERROR MESSAGES:

QRI - (NAME) DOES NOT EXIST
THE FILE *NAME* IS NOT A LOCAL FILE OR A LIBRARY MACRO RECORD NAME.

QRI - INVALID OPTION - XX

THE OPTION -XX- WAS NOT A VALID FILE
REFORMATTING OPTION RECOGNIZED BY *QRI*.

QRP - RESTORE SYSTEM PARAMETERS

QRP

RESTORES THE SYSTEM PARAMETERS -E-, -Q-, -W-, -W1-, AND -X-
TO THE VALUES USED BEFORE THE LAST USE OF THE *QS* OPERATOR.

QRUN - RUN ANOTHER EMESAE PROGRAM

QRU(N), PNAME[, ARG1][, ARG2] ... [, ARGN]

WHERE:

PNAME IS THE NAME OF A EMESAE PROGRAM TO BE EXECUTED.
ARG1 - *ARGN* ARE THE OPTIONAL ARGUMENTS FOR THE
PROGRAM AS THEY WOULD OCCUR ON A STANDARD
MACE CONTROL CARD.
A TERMINATOR CHARACTER IS NOT REQUIRED AFTER THE LAST
ARGUMENT.

ERROR MESSAGES:

QRU - ERROR DETECTED BY (PNAME)
THE EMESAE PROGRAM -PNAME- RETURNED WITH
AN ABORT RESPONSE.

QSEND - SEND A JOB TO THE BATCH SYSTEM

QSE(N), JOBNAME[, DATA1][, DATA2] ... [DATAN]

THE FILE *JOBCA* WILL BE USED AS THE CONTROL CARD
RECORD FOR THE JOB.
THE FIRST LINE OF THE FILE *JOBCA* MUST CONTAIN A VALID
EMACEE JOBCARD. THE SECOND LINE MUST CONTAIN A
PASSWORD CARD IF THE ACCOUNT NUMBER IS PROTECTED
WITH A NON-NULL PASSWORD.

ERROR MESSAGES:

QSE - NO JOBNAME

THE JOBNAME WAS NULL OR OMITTED.

QSE - ILLEGAL COMMAND FROM BATCH

NO JOBS MAY BE SENT TO OR ACCESSED FROM THE BATCH SYSTEM FROM A BATCH PIRATE JOB.

QSE - NO JOBCARD FILE

THERE WAS NO FILE CONTAINING THE JOBCARD AND CONTROL CARDS FOR THE JOB.

QSE - (NAME) IS A LOCAL FILE

THE NAME FORMED BY CONCATENATING THE TERMINAL ID CHARACTERS TO THE NAME GIVEN AS THE JOBNAME ALREADY EXISTED AS A LOCAL FILE.

QSE - (NAME) IS NOT A LOCAL FILE

THE FILE, *NAME*, WHICH WAS SPECIFIED AS A DATA FILE FOR THE JOB WAS NOT A LOCAL FILE.

QSE - NULL JOBCARD RECORD ON (NAME)

THE FIRST LINE READ FROM THE FILE, *NAME*, WAS AN END OF RECORD.

QSE - EXCESSIVE JOBS IN BATCH SYSTEM

NO MORE JOBS MAY BE SUBMITTED UNTIL THE NUMBER OF BATCH JOBS FROM THIS TERMINAL HAS DECREASED.

JOBCARD ERROR ... XXXXXXXXXXXXXXXXXXXXXXXX

THE JOBCARD OF THE JOB WAS NOT LEGAL FOR THE REASON GIVEN. THE JOB WAS NOT SENT TO THE BATCH SYSTEM.

QSHOW - SHOW PARAMETER VALUES

QSH[OW], PARM1[-PARM2]

DISPLAYS THE VALUES OF ANY SUBSTITUTABLE PARAMETER OR RANGE OF PARAMETERS.

WHERE:

PARM1 IS THE NAME OF THE FIRST PARAMETER VALUE TO BE DISPLAYED.

PARM2, IF SPECIFIED, IS THE NAME OF THE LAST PARAMETER VALUE TO BE DISPLAYED.

ERROR MESSAGES:

QSH - ILLEGAL ARGUMENT RANGE, XX - YY
 -XX- AND -YY- MUST BE FROM THE SAME
 PARAMETER NAME.

QSP - SAVE SYSTEM PARAMETERS

QSP[,FORCE]

SAVES THE SYSTEM PARAMETERS -E-, -Q-, -W-, -W1-, AND -X- AND
 SETS THE CURRENT VALUES TO THE SYSTEM DEFAULTS.

IF A PARAMETER IS NOT SUPPLIED, THE PARAMETERS WILL ONLY BE
 SAVED IF NO OTHER *QSP* OPERATOR HAS BEEN USED SINCE THE
 LAST USE OF THE *QRP* OPERATOR.

IF AN ARGUMENT IS SUPPLIED, THE CURRENT PARAMETERS WILL BE
 SAVED, DESTROYING ANY PREVIOUSLY SAVED VALUES.

QSTATISTICS - LIST RUN STATISTICS

QST[ATISTICS][,<OPT>]

WHERE: <OPT> MAY BE ANY OF THE FOLLOWING

- ALL- LIST ALL STATISTICS
- COUNT- LIST OPERATOR AND COMMAND COUNTS
- CHARS- LIST CONTROL CHARACTERS
- STORAGE- LIST STORAGE MANAGEMENT COUNTS
- SYSTEM- LIST SYSTEM REQUEST COUNTS
- TIME- LIST CP TIME AND IO UNITS USED

-COUNT- IS ASSUMED IF NO ARGUMENTS ARE SUPPLIED.

ONLY THE FIRST TWO CHARACTERS ARE SIGNIFICANT.

UNRECOGNIZED OPTIONS WILL BE IGNORED WITHOUT COMMENT.

QSUBTRACT - SUBTRACT PARAMETER VALUES

QSU[BTRACT], PARM1[, PARM2][, R][, R]
 ARGUMENTS ARE IDENTICAL TO *ADD*.

QTMESAGE - SEND A MESSAGE TO THE USER TERMINAL

QTM Q MESSAGE Q

WHERE:

Q IS THE CURRENT QUOTE CHARACTER.

QTRACE - SET MACRO COMMAND TRACE

QTR[ACE],[SW][,SUP]

SW = ACTIVATION/DEACTIVATION FLAG

-ON- TURNS TRACE ON

-OFF- TURNS TRACE OFF.

-(NULL)- TOGGLES TRACE FLAG OFF/ON/OFF

UNRECOGNIZED ARGUMENTS ARE CONSIDERED AS -ON-.

SUP = LINE NUMBER SUPPRESSION FLAG. IF -SJP- LINE

NUMBERS WILL NOT BE INCLUDED ON TRACE OUTPUT. IF

ANY OTHER NON-NULL ARGUMENT, IT WILL FORCE LINE

NUMBERS TO BE INCLUDED ON TRACE OUTPUT.

QTYPE - SET TERMINAL TYPE CHARACTERISTICS

QTY[PE],[DEVICE],[DUPLEX],[WIDTH],[DEPTH],[EJECT]

DEVICE = DEVICE CODE:

K = KSR TELETYPE OR EQUIVALENT.

T = ASR PAPER TAPE CAPABLE TELETYPE.

I = IBM 1050 TERMINAL.

E = EBCDIC TERMINAL.

C = PTTC CORRESPONDENCE CODE TERMINAL.

DUPLEX = DUPLEX MODE:

H = SET HALF DUPLEX.

F = SET FULL DUPLEX.

WIDTH = PAGE WIDTH IN CHARACTERS. (0 ≤ W < 148)

DEPTH = NUMBER OF LINES PER TEXT PAGE FOR CRT DEVICES.

EJECT = NUMBER OF LINES TO SPACE AFTER -DEPTH- LINES

FOR TTY TYPE DEVICES.

ERROR MESSAGES:

QTY - INVALID DUPLEX - DD

DUPLEX SPECIFIED NOT *HALF* OR *FULL*.

- QTY - INVALID PAGE WIDTH - WW
THE PAGE WIDTH SPECIFIED COULD NOT BE
CONVERTED TO A DECIMAL INTEGER.
- QTY - ILLEGAL PAGE DEPTH - DD
THE PAGE DEPTH VALUE SPECIFIED COULD NOT
BE CONVERTED TO A DECIMAL INTEGER.
- QTY - INVALID EJECT COUNT - EF
THE SPECIFIED EJECT LINE COUNT COULD NOT
BE CONVERTED TO A DECIMAL INTEGER.

IN THE FUTURE *QTY* WILL BE REPLACED BY THE MORE GENERALIZED

QEN. SEE DOCUMENTATION ON PREVIOUS PAGES.

QWRITE - WRITE A FILE IN EXTERNAL MODE

QWR[ITE],FILE[,OPTIONS]

FILE WILL BE WRITTEN IN EXTERNAL MODE WITH THE OPTIONS
SPECIFIED. IF NO OPTIONS ARE SPECIFIED AND THE FILE IS
ALREADY IN EXTERNAL MODE, NO ACTION WILL BE TAKEN.

OPTIONS MAY BE ANY FILE OR LINE REFORMATTING OPTION, AND
CO TO WRITE THE FILE IN COMPRESSED FORMAT.

IF THE FILE IS THE CURRENT MACRO INPUT FILE, CONTROL WILL
RETURN TO COMMAND MODE AFTER THIS OPERATOR.

ERROR MESSAGES:

- QWR - MISSING FILE NAME
NO FILE NAME WAS SPECIFIED.
- QWR - (NAME) DOES NOT EXIST
NAME WAS NOT A LOCAL FILE.
- QWR - INVALID OPTION - XX
THE OPTION -XX- IS NOT A VALID FILE
REFORMATTING OPTION RECOGNIZED BY *QWRITE*.
- QWR - NO LINES WRITTEN FROM - (NAME)
THE FIRST LINE SPECIFIED OF THE FILE,
NAME, COULD NOT BE LOCATED.

QXCOMNT - SEND A MESSAGE TO USER TERMINAL WITH IMMEDIATE

COMMAND ENTRY.

QXC[OMNT] Q MESSAGE Q [Q REPROMPT MESSAGE Q]

WHERE: *Q* IS THE QUOTE CHARACTER.

QXC WILL WAIT FOR USER INPUT OF A COMMAND.

IF A *RUBOUT* CHARACTER IS ENTERED BY THE USER,
THE FIRST TEN CHARACTERS OF THE REPROMPT MESSAGE WILL
BE ISSUED.

QXMIT - TRANSMIT A JOB TO THE BATCH SYSTEM

QXM[IT],JOBNAME,CCFILE[,DATA1][,DATA2] ... [,DATA1]

CCFILE MUST CONTAIN A VALID JOBCARD AS ITS FIRST CARD.

THE ERROR MESSAGES FOR *QXMIT* ARE IDENTICAL TO THE ERROR
MESSAGES FOR *QSEND* EXCEPT FOR THE FIRST 3 CHARACTERS WHICH
WILL BE -QXM- FOR ALL -QXMIT- ERRORS.

USERS - DISPLAY NUMBER OF ACTIVE USERS

USE[RS]

INDEX

BROADCAST	8
CHECK	8
Command Line Syntax	5
CTL	8
File Name Requirements	3
File Structure	2
GOTO	8
IFEQUAL	9
IFGT	9
IFLT	9
IFNOTEQUAL	9
JOBCARD	10
LABEL	10
LOG	10
PARAMETERS	10
Parameter Error Messages	6
Parameter Substitution	7
PROCSY - PIRATE Incompatibilities	4
QACCESS	11
QADD	14
QAPPEND	14
QASSIGN	15
QBROADCAST	8
QCLOSE	16
QCONVERT	16
QCREATE	17
QDELETE	17
QDISPLAY	18
QDVIDE	18
QEDIT	18
QEN	20
QERROR	21
QEXCHANGE	21
QFILES	22
QFLUSH	22
QHOLD	23
QINSERT	23
QIQUIRE	23
QLIBRARY	23
QLL	24
QMULTIPLY	24
QPAUSE	24
QRENAME	24
QRI	25
QRP	26
QRUN	26
QSEND	26
QSHOW	27
QSP	28

QSTATISTICS	28
QSUBTRACT	28
QTMESSAGE	29
QTRACE	29
QTYPE	29
QWRITE	30
QXCOMNT	31
QXMIT	31
Reformatting Options	5
USERS	31